

## 短信 API HTTP 接口

群发短信发送接口 用户通过 HTTP 的 POST 或 GET 方式提交短信发送请求。采用 UTF-8 编码。

请求地址

环境 HTTP 请求地址

正式环境 <http://ad1200.now.net.cn:2003/sms/sendSMS> 请求参数

名称	类型	是否必须	示例值	描述
userId	Integer	必须	xxxxxxxxxx	平台分配给用户的短信用户 ID 号(去掉 ms 开头)
password	String	必须	yyyyyyyyyy	平台分配给用户的密码
apiType	Integer	必选	51	平台上申请的 API 接口类型(发送通道类型 <a href="http://www.now.cn/mobile-admin/sms_manager.php?IDSMSUser=xx">http://www.now.cn/mobile-admin/sms_manager.php?IDSMSUser=xx</a> )
mobile	String	必选	13900000000,13900000001	接收短信的手机号码, 多个号码以半角逗号, 隔开

content	String	必选	时代互联欢迎您	发送的短信内容, 采用 utf8 编码 /* ---示例代码 GET 方式 ----*/ http://ad1200.now.net.cn:2003/sms/sendSMS?userId=10xx&password=ndxx&apiType=51&mobile=1361222xx,1888xx&content= 尊敬的用户 xx /* ---示例代码 POST 方式----*/ package java_test;
---------	--------	----	---------	---

```

import java.io.BufferedReader;
import java.io.InputStreamReader;
import java.io.PrintWriter;
import java.net.URL;
import java.net.URLConnection;
import java.net.URLEncoder;
public class SMSTest {
    public static void main(String[] args) {
        // TODO Auto-generated method stub
        PrintWriter out = null;
        BufferedReader in = null;
        String m_Response = "";
        try {
            String s = "时代互联欢迎您";
            String params = "userId=10xx"
                + "&password=mtxx"
                + "&apiType=2"
                + "&content="+ URLEncoder.encode(s, "UTF-8")
                + "&mobile=136xx,139xx" ;
            String url = "http://ad1200.now.net.cn:2003/sms/sendSMS";
            URL realUrl = new URL(url);
            URLConnection conn = realUrl.openConnection();

```

```

        conn.setRequestProperty("accept", "*/*");
        conn.setRequestProperty("connection", "Keep-Alive");
        conn.setRequestProperty("user-agent", "Mozilla/4.0 (compatible; MSIE 6.0;
        Windows NT 5.1; SV1)");
        conn.setDoOutput(true);
        conn.setDoInput(true);
        out = new PrintWriter(conn.getOutputStream());
        out.print(params);
        out.flush();
        in = new BufferedReader(new InputStreamReader(conn.getInputStream()));
        String line = null;
        while ((line = in.readLine()) != null)
            m_Response += line;
    } catch (Exception e) {
        e.printStackTrace();
    } finally {
        try {
            if (out != null)
                out.close();
        } catch (Exception localException) {
        }
        try {
            if (in != null)
                in.close();
        } catch (Exception localException) {
        }
        in = null;
    }
    System.out.println("m_Response=" + m_Response);
}
}

```

/\* ---示例代码 POST 方式----\*/

JAVA 格式

响应示例

```

{
code: "0",
msg: "SUCCESS",
}

```

错误码 错误描述

- 1 userld is illegal
- 2 user is not exist
- 3 your IP is limit
- 4 authorize failed
- 5 user is stop

- 6 user is not active
- 7 user is delete
- 8 user is no money
- 9 用户接口异常
- 10 获取用户接口异常
- 11 短信内容编码异常
- 13 号码群不合规范
- 14 your account is not enough to send
- 15 您重复发送同一号码超过了六十次，您的账号已被停用，请联系客服开通.
- 16 发送异常，请联系客服开通.
- 17 发送失败: